



# **Delivering Toxic Release Inventory Transfer Data**

By Joey Coscia and Ryne Yarger  
Velu Senthil





## What is the Toxics Release Inventory (TRI) Program?

- Created Under the Emergency Planning & Community Right-to-Know Act (EPCRA) of 1986, and Pollution Prevention Act (PPA) of 1990.
- TRI is an information resource that provides information about toxic chemical releases and other waste management activities from certain facilities in your neighborhood.
- Facilities in certain industry sectors are required to report to EPA, states, and tribal governments each year
  - ❖ If they manufacture or process more than 25,000 lbs, or otherwise use more than 10,000 lbs annually of a chemical included on the TRI list of toxic chemicals
    - ❖ Non-PBT's
      - On-site releases (air, land, and water).
      - Waste management (i.e., Release, Recycling, Treatment, Energy recovery).
      - Pollution prevention activities.
      - Transfer of chemicals in waste to off-site locations.
- EPA must maintain and make the data available to the public




## Background on TRI Transfer Project

- In 2014, TRI facilities reported over 100K offsite transfers consisting of ~400 million pounds of toxic chemicals for release and other waste management activities
- Three types of major facilities that receive chemicals in waste
  - Section 6.1 Publicly Owned Treatment Works (POTWs)
  - Section 6.2 Receiving Facilities with RCRA IDs
  - Section 6.2 Receiving Facilities without RCRA IDs
- This project aims to expand the scope from previous projects focusing on Section 6.2





## TRI Transfer Project Site Depiction




<http://smithculp.com/wp-content/uploads/2013/01/waste-water-planning.jpg>




## How do we want to visualize TRI Transfers?

- Purpose of project: Visualization of TRI offsite transfers






# Qlik Sense




2015 TRI Data 2015 TRI Mapping

No selections applied

Facility Name	Total Offsite Recovery
DELTA COS GROUP BA OLYMPIC OIL	0
DELTA COS GROUP BA OLYMPIC OIL	0
ST AYD CORP	NA
A COMPOSITES US INC	NA
S MERMET	0
S MERMET	0
M ASTON	0
M ASTON	0
M ATLANTA	0
M ATLANTA	0
M ATLANTA	0
M ATLANTA	0
M ATLANTA	0
M ATLANTA	0
M ATLANTA	0



Total	Total	Total
0	0	19484
0	0	9460
0	1420	0





# ArcGIS

Table Of Contents

Layers

- C:\Users\jcoscia\Documents\2015 TRI GIS Project\July 2015\Mini\_
- All\_TRI\_Transferring\_Facilities\_small
- C:\Users\jcoscia\Documents\2015 TRI GIS Project\July 2015\Mini\_
- All\_TRI\_Transferring\_Facilities\_small
- C:\Users\jcoscia\Documents\2015 TRI GIS Project\July 2015\Receiv\_
- All\_Receiving\_Facilities
- C:\Users\jcoscia\Documents\2015 TRI GIS Project\July 2015\TRI Fa
- TRI\_Facilities\_Transfer\_Only
- TRI\_Facilities\_Onsite\_Releases\_Only
- TRI\_Facilities\_Both\_Onsite\_Release\_and\_Transfers
- C:\Users\jcoscia\Documents\2015 TRI GIS Project\July 2015\TRI Fa
- TRI\_Facilities\_All
- All\_TRI\_Transferring\_Facilities
- C:\Users\jcoscia\Documents\2015 TRI GIS Project\July 2015\TRI\_T
- Transfers\_for\_Recovery\_small
- Transfers\_for\_Recovery (small)
- Transfers\_for\_Treatment

Catalog

Location: Home - 2015 TRI GIS Project\July 2015

- Home - 2015 TRI GIS Project\July 2015
- Folder Connections
  - C:\Users\jcoscia\Documents
  - C:\Users\jcoscia\Documents\2015 TRI GIS Project\July 2015
  - C:\Users\jcoscia\Documents\2016 TRI GIS Project\July 2015
  - C:\Users\jcoscia\Documents\2016 TRI GIS Project\July 2015
- Toolboxes
- Database Servers
- Database Connections
- GIS Servers
  - Add ArcGIS Server
  - Add ArcIMS Server
  - Add WCS Server
  - Add WMS Server
  - Add WMTS Server
  - arcgis on igeo.epa.gov (user)
- My Hosted Services
- Ready-To-Use Services



## Data Cleansing/Data Prep

- Geocoded addresses  $\longrightarrow$  X,Y coordinates
- Data Supplied by Tim Antidel
  - Innovate!
    - Mark Murphy
- Data Inconsistency
  - Address Correction
    - Arc Catalog
    - Review/Rematch tool

Shape	Loc_name	Stat	Sco	Match	Match_addr	Addr_type
Point	USA.StreetAddress	M	100	A	11397 Road 176, Paulding, Ohio, 45879	StreetAddress
Point	USA.PointAddress	M	100	A	2800 E 90th St, Cleveland, Ohio, 44104	PointAddress
Point	USA.PointAddress	M	100	A	2869 Sandstone Dr, Hatfield, Pennsylvania,	PointAddress

Loc_name	Score	Side	Match_addr
USA.Postal	100		44104, Cleveland, Ohio
USA.AdminPlaces	100		Cleveland, Ohio
USA.AdminPlaces	96.54		East Cleveland, Ohio
USA.AdminPlaces	96.54		Cleveland Heights, Ohio





# Creating the Initial Shapefiles

- ArcToolbox
  - 3D Analyst Tools
  - Analysis Tools
  - Cartography Tools
  - Conversion Tools
  - Data Interoperability Tools
  - Data Management Tools
    - Archiving
    - Attachments
    - Data Comparison
    - Distributed Geodatabase
    - Domains
    - Feature Class
    - Features
      - Add Geometry Attributes
      - Add XY Coordinates
      - Adjust 3D Z
      - Bearing Distance To Line
      - Check Geometry
      - Copy Features
      - Delete Features
      - Dice
      - Feature Envelope To Polygon
      - Feature To Line
      - Feature To Point
      - Feature To Polygon
      - Feature Vertices To Points
      - Geodetic Densify
      - Minimum Bounding Geometry
      - Multipart To Singlepart
      - Points To Line
      - Polygon To Line
      - Repair Geometry
      - Split Line at Point
      - Split Line At Vertices
      - Table To Ellipse
      - Unsplit Line
      - XY To Line**

Display XY Data

A table containing X and Y coordinate data can be added to the map as a layer

Choose a table from the map or browse for another table:

TRI\_RCRA\_LAT\_LON\_Chemicals\_revised.csv

Specify the fields for the X, Y and Z coordinates:

X Field: TRI\_LON

Y Field: TRI\_LAT

Z Field: <None>

Coordinate System of Input Coordinates

Description:

Geographic Coordinate System:  
Name: GCS\_North\_American\_1983

XY To Line

Input Table: IRISource\_All

Output Feature Class: C:\Users\Owner\Documents\ArcGIS\Default.gdb\TRISource\_All\_XYToLine

Start X Field: TRI\_LON

Start Y Field: TRI\_LAT

End X Field: RCRA\_LON

End Y Field: RCRA\_LAT

Line Type (optional): GEODESIC


ID (optional): UniqueID

Spatial Reference (optional): GCS\_North\_American\_1983

OK Cancel Environment... Show Help >>



# Facilities Involved in Transferring or Receiving TRI Chemicals






## Establishing the Web Service

- Establish access to the NCC Servers
  - proper map symbology through NCC staging
- Share GIS map as a “Map Service”
- Geoplatform access
  - web application

Qi Dai



ONE  EPA  
Workplace  
GeoPlatform





## Live Demo

<https://epa.maps.arcgis.com/apps/webappviewer/index.html?id=4f9d3a5e31c945bb920431db4d5eb359>

ONE  EPA  
Workplace  
GeoPlatform





## In Conclusion


- Searchability of TRI transfer data
  - User friendly interface
  - Community's respond well to maps
- Questions?



2015 TRI Waste Transfers (small)-Copy


Esri World Geocoder

Map navigation and tool icons: zoom in (+), zoom out (-), search (magnifying glass), layers, scale bar, north arrow, location pin, and other navigation controls.



2015 TRI Waste Transfers (small)-Copy

Chicago, Illinois, United Sta




2015 TRI Waste Transfers (small)-Copy

Map navigation and tool icons including zoom in (+), zoom out (-), search (Chicago, Illinois, United Sta), legend, layer list, measurement tool, and other standard GIS interface elements.



**Analysis**

 **Trace Downstream**

---

**Messages**


- Trace Downstream submitted.
- Executing
- Succeeded.

**Outputs**

[Drawn Input Points TraceJoey](#)

Note: Feature and table outputs are added in the map as operational layers.

**Back**   **Home**



2015 TRI Waste Transfers (small)-Copy

Chicago, Illinois, United Sta

